
## Transferring Project Files via Wireless Wi-Fi

The wireless Wi-Fi feature is supported on TOPR Premium models and TOPRH Wireless models.


This guide explains how to connect via Wi-Fi and transfer project files from your PC to the TOP device.

## 1.1 Check Wi-Fi Settings on the PC


1. Open the [Control Panel] on your PC and go to [Network and Internet].




2. Select [Network and Sharing Center].




3. Click [Change adapter settings].




4. Right-click your **Wi-Fi** adapter and select **[Properties]**.



5. Select [Internet Protocol Version 4 (TCP/IPv4)] and click [Properties].





6. Note down your IP address, Subnet mask, Default gateway, Preferred DNS Server (DNS1), and Alternate DNS server (DNS2) settings.

When configuring Wi-Fi on the TOP device:


- The **first three octets** of the IP address must be the same as your PC's.
- The **last octet** must be different.
- Subnet, Gateway, DNS1, and DNS2 must be identical to the PC's settings.

## 1.2 Configure Wi-Fi on the TOP Device

1. On the TOP device, open [Control Panel] - [System] - [Wi-Fi].




- 2. The Wi-Fi screen will display available networks in the left panel.
- 3. Select the network you wish to connect to and click [Connect].



- 4. Set the IP mode to [Manual], then enter the IP/Subnet/Gate/DNS1/DNS2 values:
  - o IP address: First three octets match the PC, last octet is different.
  - Subnet, Gateway, DNS1, DNS2: Same as the PC.

## 1.3 Connect via Wi-Fi in TOP Design Studio and Transfer the Project

- 1. In TOP Design Studio, press F9 or go to [Trans] [Full Build & Transfer].
- 2. After the build is complete, the [Connection Setting] window will appear.
- 3. Set the connection type to [Ethernet] the [PC IP] address will be displayed automatically.
- 4. To search the TOP device:
  - o Adjust the [Range], or
  - o Enter the TOP device's IP address directly in [IP direct input] and click [Search].



5. When the TOP device is found, its details will appear under [Information].



6. Click **[OK]** to begin transferring the project file.